

Quick Guide to the WLX Pro Update tool

To update the firmware of a **WLX Pro cylinder/repeater**, you require the following accessories:

1 x WLX Pro Updater cable

1 x WLX Pro Updater software



For using WLX Pro Updater Software a computer with **Windows 10 or higher** operating system is required.

Key:




Connect



Disconnect




FW Update


	<ol style="list-style-type: none">1. Open the WLX Pro Updater software2. Insert the WLX Pro Updater cable into the serial USB port of the laptop.3. Insert the micro USB plug into the serial port of the component. (cylinder briefly lights up green)4. Under "Select USB", select the COM port5. Click on the "Connect" symbol
---	---




Next, click on the FW Update symbol



1. Select the new firmware
2. Click on "Update"



Update process is performed



When the update is complete, the cylinder initialises and returns to its original state